# pylxd Documentation

**Canonical Ltd** 

## Contents

1	Installation	3
2	Getting started 2.1 Client	5
3		7
4	Events	9
5	Certificates15.1 Manager methods15.2 Certificate attributes1	l 1
6	Containers         1           6.1 Manager methods         1           6.2 Container attributes         1           6.3 Container methods         1           6.4 Examples         1           6.5 Container Snapshots         1           6.6 Container files         1	13 14 14
7	Images         1           7.1 Manager methods         1           7.2 Image attributes         1           7.3 Image methods         2           7.4 Examples         2	19
8	Networks28.1 Manager methods28.2 Network attributes28.3 Network methods28.4 Examples2	23
9	Profiles9.1 Manager methods29.2 Profile attributes2	

			25 26
10	10.2 10.3	Manager methods	27 27 27 27
11			28 <b>29</b>
11		Manager methods	29 29 29
12	12.1 12.2	Storage Pool objects	31 31 32 33
13		Cluster object	<b>35</b> 35 36
14	14.1 14.2 14.3	Adding a Feature or Fixing a Bug	37 37 37 38 38
15	15.1 (15.2 15.3 (15.4 15.5 15.6 15.7 15.8 (15.9 15.10 15.11 )	Client Exceptions Certificate Container Virtual Machine Image Network Operation Profile Project Storage Pool	41 42 43 43 47 47 48 49 50 50 53
16	Indice	es and tables	55
Inc	lex		57

n۱	/lxd	D٥	CHI	ner	ntat	ion

Contents:

Contents 1

2 Contents

					4
CH	Α	PT	F	R	

Installation

#### If you're running on Ubuntu Xenial or greater:

sudo apt install python-pylxd lxd

#### Otherwise you can track LXD development on other Ubuntu releases:

sudo add-apt-repository ppa:ubuntu-lxc/lxd-git-master && sudo apt update sudo apt install lxd

#### Or install pylxd using pip:

pip install pylxd

Getting started

### 2.1 Client

Once you have *installed*, you're ready to instantiate an API client to start interacting with the LXD daemon on local-host:

```
>>> from pylxd import Client
>>> client = Client()
```

If your LXD instance is listening on HTTPS, you can pass a two part tuple of (cert, key) as the cert argument.

Note: in the case where the certificate is self signed (LXD default), you may need to pass *verify=False*.

### 2.1.1 Querying LXD

LXD exposes a number of objects via its REST API that are used to orchestrate containers. Those objects are all accessed via manager attributes on the client itself. This includes *certificates*, *containers*, *images*, *networks*, *operations*, and *profiles*. Each manager has methods for querying the LXD instance. For example, to get all containers in a LXD instance

```
>>> client.containers.all()
[<container.Container at 0x7f95d8af72b0>,]
```

For specific manager methods, please see the documentation for each object.

#### 2.1.2 pylxd Objects

Each LXD object has an analogous pylxd object. Returning to the previous *client.containers.all* example, a *Container* object is manipulated as such:

```
>>> container = client.containers.all()[0]
>>> container.name
'lxd-container'
```

Each pylxd object has a lifecycle which includes support for transactional changes. This lifecycle includes the following methods and attributes:

- *sync()* Synchronize the object with the server. This method is called implicitly when accessing attributes that have not yet been populated, but may also be called explicitly. Why would attributes not yet be populated? When retrieving objects via *all*, LXD's API does not return a full representation.
- dirty After setting attributes on the object, the object is considered "dirty".
- rollback() Discard all local changes to the object, opting for a representation taken from the server.
- save() Save the object, writing changes to the server.

Returning again to the Container example

```
>>> container.config
{ 'security.privileged': True }
>>> container.config.update({'security.nesting': True})
>>> container.dirty
True
>>> container.rollback()
>>> container.dirty
False
>>> container.config
{ 'security.privileged': True }
>>> container.config = {'security.privileged': False}
>>> container.save(wait=True) # The object is now saved back to LXD
```

### 2.1.3 A note about asynchronous operations

Some changes to LXD will return immediately, but actually occur in the background after the http response returns. All operations that happen this way will also take an optional *wait* parameter that, when *True*, will not return until the operation is completed.

### 2.1.4 UserWarning: Attempted to set unknown attribute "x" on instance of "y"

The LXD server changes frequently, particularly if it is snap installed. In this case it is possible that the LXD server may send back objects with attributes that this version of pylxd is not aware of, and in that situation, the pylxd library issues the warning above.

The default behaviour is that *one* warning is issued for each unknown attribute on *each* object class that it unknown. Further warnings are then surpressed. The environment variable PYLXD\_WARNINGS can be set to control the warnings further:

- if set to none then all warnings are surpressed all the time.
- if set to always then warnings are always issued for each instance returned from the server.

### **Client Authentication**

When using LXD over https, LXD uses an asymmetric keypair for authentication. The keypairs are added to the authentication database after entering the LXD instance's "trust password".

#### 3.1 Generate a certificate

To generate a keypair, you should use the *openssl* command. As an example:

```
openssl req -newkey rsa:2048 -nodes -keyout lxd.key -out lxd.csr openssl x509 -signkey lxd.key -in lxd.csr -req -days 365 -out lxd.crt
```

For more detail on the commands, or to customize the keys, please see the documentation for the *openssl* command.

## 3.2 Authenticate a new keypair

If a client is created using this keypair, it would originally be "untrusted", essentially meaning that the authentication has not yet occurred.

```
>>> from pylxd import Client
>>> client = Client(
... endpoint='http://10.0.0.1:8443',
... cert=('lxd.crt', 'lxd.key'))
>>> client.trusted
False
```

In order to authenticate the client, pass the lxd instance's trust password to Client.authenticate

```
>>> client.authenticate('a-secret-trust-password')
>>> client.trusted
>>> True
```

**Events** 

LXD provides an /events endpoint that is upgraded to a streaming websocket for getting LXD events in real-time. The Client's events method will return a websocket client that can interact with the web socket messages.

```
>>> ws_client = client.events()
>>> ws_client.connect()
>>> ws_client.run()
```

A default client class is provided, which will block indefinitely, and collect all json messages in a *messages* attribute. An optional *websocket\_client* parameter can be provided when more functionality is needed. The *ws4py* library is used to establish the connection; please see the *ws4py* documentation for more information.

The stream of events can be filtered to include only specific types of events, as defined in the LXD /endpoint documentation.

To receive all events of type 'operation' or 'logging', generated by the LXD server:

```
>>> filter = set([EventType.Operation, EventType.Logging])
>>> ws_client = client.events(event_filter=filter)
```

To receive only events pertaining to the lifecycle of the containers:

```
>>> filter = set([EventType.Lifecycle])
>>> ws_client = client.events(event_filter=filter)
```

10 Chapter 4. Events

### Certificates

Certificates are used to manage authentications in LXD. Certificates are not editable. They may only be created or deleted. None of the certificate operations in LXD are asynchronous.

### 5.1 Manager methods

Certificates can be queried through the following client manager methods:

- *all()* Retrieve all certificates.
- get() Get a specifit certificate, by its fingerprint.
- create() Create a new certificate. This method requires a first argument that is the LXD trust password, and the cert data, in binary format.

### 5.2 Certificate attributes

Certificates have the following attributes:

- fingerprint The fingerprint of the certificate. Certificates are keyed off this attribute.
- certificate The certificate itself, in PEM format.
- type The certificate type (currently only "client")

#### Containers

Container objects are the core of LXD. Containers can be created, updated, and deleted. Most of the methods for operating on the container itself are asynchronous, but many of the methods for getting information about the container are synchronous.

## 6.1 Manager methods

Containers can be queried through the following client manager methods:

- exists(name) Returns boolean indicating if the container exists.
- *all()* Retrieve all containers.
- get() Get a specific container, by its name.
- create(config, wait=False) Create a new container. This method requires the container config as the first parameter. The config itself is beyond the scope of this documentation. Please refer to the LXD documentation for more information. This method will also return immediately, unless wait is True.

### 6.2 Container attributes

For more information about the specifics of these attributes, please see the LXD documentation.

- architecture The container architecture.
- config The container config
- created\_at The time the container was created
- devices The devices for the container
- ephemeral Whether the container is ephemeral
- expanded\_config An expanded version of the config

- expanded\_devices An expanded version of devices
- name (Read only) The name of the container. This attribute serves as the primary identifier of a container
- description A description given to the container
- profiles A list of profiles applied to the container
- status (Read only) A string representing the status of the container
- last used at (Read only) when the container was last used
- status\_code (Read only) A LXD status code of the container
- stateful (Read only) Whether the container is stateful

#### 6.3 Container methods

- rename Rename a container. Because name is the key, it cannot be renamed by simply changing the name of the container as an attribute and calling save. The new name is the first argument and, as the method is asynchronous, you may pass wait=True as well.
- save Update container's configuration
- *state* Get the expanded state of the container.
- start Start the container
- stop Stop the container
- restart Restart the container
- freeze Suspend the container
- unfreeze Resume the container
- execute Execute a command on the container. The first argument is a list, in the form of subprocess. Popen with each item of the command as a separate item in the list. Returns a tuple of (exit\_code, stdout, stderr). This method will block while the command is executed.
- raw\_interactive\_execute Execute a command on the container. It will return an url to an interactive websocket and the execution only starts after a client connected to the websocket.
- *migrate* Migrate the container. The first argument is a client connection to the destination server. This call is asynchronous, so wait=True is optional. The container on the new client is returned. If live=True is passed to the function call, then the container is live migrated (see the LXD documentation for further details).
- *publish* Publish the container as an image. Note the container must be stopped in order to use this method. If *wait=True* is passed, then the image is returned.
- restore\_snapshot Restore a snapshot by name.

## 6.4 Examples

If you'd only like to fetch a single container by its name...

```
>>> client.containers.get('my-container')
<container.Container at 0x7f95d8af72b0>
```

If you're looking to operate on all containers of a LXD instance, you can get a list of all LXD containers with all.

```
>>> client.containers.all()
[<container.Container at 0x7f95d8af72b0>,]
```

In order to create a new Container, a container config dictionary is needed, containing a name and the source. A create operation is asynchronous, so the operation will take some time. If you'd like to wait for the container to be created before the command returns, you'll pass wait=True as well.

```
>>> config = {'name': 'my-container', 'source': {'type': 'none'}}
>>> container = client.containers.create(config, wait=False)
>>> container
<container.Container at 0x7f95d8af72b0>
```

If you were to use an actual image source, you would be able to operate on the container, starting, stopping, snapshotting, and deleting the container. You can also modify container config (limits and etc).

Config line with a specific image source and a profile.

```
>>> config = {'name': 'my-container', 'source': {'type': 'image', "mode": "pull",

"server":

"https://cloud-images.ubuntu.com/daily", "protocol": "simplestreams", 'alias':

'bionic/amd64'},

'profiles': ['profilename'] }
```

To modify container's configuration method ' 'should be called after Container attributes changes.

```
>>> container = client.containers.get('my-container')
>>> container.ephemeral = False
>>> container.devices = { 'root': { 'path': '/', 'type': 'disk', 'size': '7GB'} }
>>> container.save()
```

To get state information such as a network address.

```
>>> addresses = container.state().network['eth0']['addresses']
>>> addresses[0]
{'family': 'inet', 'address': '10.251.77.182', 'netmask': '24', 'scope': 'global'}
```

To migrate a container between two servers, first you need to create a client certificate in order to connect to the remote server

openssl req -newkey rsa:2048 -nodes -keyout lxd.key -out lxd.csr openssl x509 -signkey lxd.key -in lxd.csr -req -days 365 -out lxd.crt

Then you need to connect to both the destination server and the source server, the source server has to be reachable by the destination server otherwise the migration will fail due to a websocket error

6.4. Examples 15

(continued from previous page)

```
cont = client_source.containers.get('testm')
cont.migrate(client_destination, wait=True)
```

This will migrate the container from source server to destination server

To migrate a live container, user the live=True parameter:

```
cont.migrate(client__destination, live=True, wait=True)
```

If you want an interactive shell in the container, you can attach to it via a websocket.

You can connect to this urls from e.g. https://xtermjs.org/.

### 6.5 Container Snapshots

Each container carries its own manager for managing Snapshot functionality. It has get, all, and create functionality.

Snapshots are keyed by their name (and only their name, in pylxd; LXD keys them by <container-name>/<snapshot-name>, but the manager allows us to use our own namespacing).

A container object (returned by get or all) has the following methods:

- rename rename a snapshot
- *publish* create an image from a snapshot. However, this may fail if the image from the snapshot is bigger than the logical volume that is allocated by lxc. See <a href="https://github.com/lxc/lxd/issues/2201">https://github.com/lxc/lxd/issues/2201</a> for more details. The solution is to increase the *storage.lvm\_volume\_size* parameter in lxc.
- restore restore the container to this snapshot.

```
>>> snapshot = container.snapshots.get('an-snapshot')
>>> snapshot.created_at
'1983-06-16T2:38:00'
>>> snapshot.rename('backup-snapshot', wait=True)
>>> snapshot.delete(wait=True)
```

To create a new snapshot, use *create* with a *name* argument. If you want to capture the contents of RAM in the snapshot, you can use *stateful=True*.

**Note:** Your LXD requires a relatively recent version of CRIU for this.

```
>>> snapshot = container.snapshots.create(
... 'my-backup', stateful=True, wait=True)
>>> snapshot.name
'my-backup'
```

### 6.6 Container files

Containers also have a *files* manager for getting and putting files on the container. The following methods are available on the *files* manager:

- put push a file into the container.
- mk\_dir create an empty directory on the container.
- recursive\_put recursively push a directory to the container.
- get get a file from the container.
- recursive\_get recursively pull a directory from the container.
- *delete\_available* If the *file\_delete* extension is available on the lxc host, then this method returns *True* and the *delete* method is available.
- delete delete a file on the container.

**Note:** All file operations use *uid* and *gid* of 0 in the container. i.e. root.

```
>>> filedata = open('my-script').read()
>>> container.files.put('/tmp/my-script', filedata)
>>> newfiledata = container.files.get('/tmp/my-script2')
>>> open('my-script2', 'wb').write(newfiledata)
```

6.6. Container files

### **Images**

*Image* objects are the base for which containers are built. Many of the methods of images are asynchronous, as they required reading and writing large files.

### 7.1 Manager methods

Images can be queried through the following client manager methods:

- all() Retrieve all images.
- get() Get a specific image, by its fingerprint.
- get\_by\_alias() Ger a specific image using its alias.

And create through the following methods, there's also a copy method on an image:

- create(data, public=False, wait=True) Create a new image. The first argument is the binary data of the image itself. If the image is public, set public to True.
- create\_from\_simplestreams(server, alias, public=False, auto\_update=False, wait=False) Create an image from simplestreams.
- create\_from\_url(url, public=False, auto\_update=False, wait=False) Create an image from a url.

## 7.2 Image attributes

For more information about the specifics of these attributes, please see the LXD documentation.

- · aliases A list of aliases for this image
- auto\_update Whether the image should auto-update
- architecture The target architecture for the image
- cached Whether the image is cached

- created\_at The date and time the image was created
- expires\_at The date and time the image expires
- filename The name of the image file
- fingerprint The image fingerprint, a sha2 hash of the image data itself. This unique key identifies the image.
- last\_used\_at The last time the image was used
- properties The configuration of image itself
- public Whether the image is public or not
- size The size of the image
- *uploaded\_at* The date and time the image was uploaded
- update\_source A dict of update informations

### 7.3 Image methods

- export Export the image. Returns a file object with the contents of the image. Note: Prior to pylxd 2.1.1, this method returned a bytestring with data; as it was not unbuffered, the API was severely limited.
- add\_alias Add an alias to the image.
- delete\_alias Remove an alias.
- copy Copy the image to another LXD client.
- *delete* Deletes the image.

### 7.4 Examples

Image operations follow the same protocol from the client's *images* manager (i.e. *get*, *all*, and *create*). Images are keyed on a sha-1 fingerprint of the image itself. To get an image...

```
>>> image = client.images.get(
... 'e3b0c44298fc1c149afbf4c8996fb92427ae41e4649b934ca495991b7852b855')
>>> image
<image.Image at 0x7f95d8af72b0>
```

Once you have an image, you can operate on it as before:

```
>>> image.public
False
>>> image.public = True
>>> image.save()
```

To create a new Image, you'll open an image file, and pass that to *create*. If the image is to be public, *public=True*. As this is an asynchonous operation, you may also want to *wait=True*.

```
>>> image_data = open('an_image.tar.gz', 'rb').read()
>>> image = client.images.create(image_data, public=True, wait=True)
>>> image.fingerprint
'e3b0c44298fc1c149afbf4c8996fb92427ae41e4649b934ca495991b7852b855'
```

Finally, delete an image. As this is an asynchonous operation, you may also want to wait=True.

20 Chapter 7. Images

```
>>> image = client.images.get(
... 'e3b0c44298fc1c149afbf4c8996fb92427ae41e4649b934ca495991b7852b855')
>>> image.delete(wait=True)
```

7.4. Examples 21

22 Chapter 7. Images

#### **Networks**

*Network* objects show the current networks available to LXD. Creation and / or modification of networks is possible only if 'network' LXD API extension is present.

## 8.1 Manager methods

Networks can be queried through the following client manager methods:

- all() Retrieve all networks.
- exists() See if a profile with a name exists. Returns bool.
- get () Get a specific network, by its name.
- create() Create a new network. The name of the network is required. description, type and config are optional and the scope of their contents is documented in the LXD documentation.

### 8.2 Network attributes

- name The name of the network.
- description The description of the network.
- type The type of the network.
- used\_by A list of containers using this network.
- config The configuration associated with the network.
- managed boolean; whether LXD manages the network.

### 8.3 Network methods

- rename () Rename the network.
- save () Save the network. This uses the PUT HTTP method and not the PATCH.
- delete() Deletes the network.

## 8.4 Examples

Network operations follow the same manager-style as other classes. Networks are keyed on a unique name.

The network can then be modified and saved.

```
>>> network.config['ipv4.address'] = '10.253.10.1/24'
>>> network.save()
```

To create a new network, use create() with a name, and optional arguments: description and type and config.

```
>>> network = client.networks.create(
... 'lxdbr1', description='My new network', type='bridge', config={})
```

**Profiles** 

Profile describe configuration options for containers in a re-usable way.

### 9.1 Manager methods

Profiles can be queried through the following client manager methods:

- all() Retrieve all profiles
- exists() See if a profile with a name exists. Returns boolean.
- get() Get a specific profile, by its name.
- create(name, config, devices) Create a new profile. The name of the profile is required. config and devices dictionaries are optional, and the scope of their contents is documented in the LXD documentation.

#### 9.2 Profile attributes

- config (dict) config options for containers
- description (str) The description of the profile
- devices (dict) device options for containers
- name (str) name of the profile
- used\_by (list) containers using this profile

#### 9.3 Profile methods

- rename Rename the profile.
- save save a profile. This uses the PUT HTTP method and not the PATCH.

• delete - deletes a profile.

### 9.4 Examples

Profile operations follow the same manager-style as Containers and Images. Profiles are keyed on a unique name.

```
>>> profile = client.profiles.get('my-profile')
>>> profile
profile at 0x7f95d8af72b0>
```

The profile can then be modified and saved.

To create a new profile, use create with a name, and optional config and devices config dictionaries.

```
>>> profile = client.profiles.create(
...     'an-profile', config={'security.nesting': 'true'},
...     devices={'root': {'path': '/', 'size': '10GB', 'type': 'disk'}})
```

26 Chapter 9. Profiles

## **Projects**

LXD supports projects as a way to split your LXD server. Each *Project* holds its own set of instances and may also have its own images and profiles.

### 10.1 Manager methods

Projects can be queried through the following client manager methods:

- all () Retrieve all projects.
- exists () See if a project with a name exists. Returns boolean.
- get () Get a specific project, by its name.
- create() Create a new project. The *name* of the project is required. *description* is an optional string with a description of the project. The *config* dictionary is also optional, the scope of which is documented in the LXD project documentation.

## 10.2 Project attributes

- name (str) name of the project.
- description (str) The description of the project.
- config (dict) config options for the project.
- used\_by (list) images, instances, networks, and profiles using this project.

## 10.3 Project methods

• rename () - Rename the project.

- save () save a project. This uses the PUT HTTP method and not the PATCH.
- delete() deletes a project.

## 10.4 Examples

Project operations follow the same manager-style as Containers and Images. Projects are keyed on a unique name.

```
>>> project = client.projects.get('my-project')
>>> project
client.project at 0x7f599e129a60>
```

The project can then be modified and saved.

```
>>> project.config['limits.instances'] = '4'
>>> project.description = "The four horsemen of the apococalypse"
>>> project.save()
```

To create a new project, use *create* with a name, optional *description* string and *config* dictionary.

```
>>> project = client.projects.create(
... 'a-project', description="New project", config={'limits.instances': '10'})
```

## Operations

*Operation* objects detail the status of an asynchronous operation that is taking place in the background. Some operations (e.g. image related actions) can take a long time and so the operation is performed in the background. They return an operation *id* that may be used to discover the state of the operation.

## 11.1 Manager methods

Operations can be queried through the following client manager methods:

- get() Get a specific operation, by its id.
- wait\_for\_operation() get an operation, but wait until it is complete before returning the operation object.

## 11.2 Operation object methods

• wait() - Wait for the operation to complete and return. Note that this can raise a LXDAPIExceptiion if the operations fails.

Storage Pools

LXD supports creating and managing storage pools and storage volumes. General keys are top-level. Driver specific keys are namespaced by driver name. Volume keys apply to any volume created in the pool unless the value is overridden on a per-volume basis.

### 12.1 Storage Pool objects

StoragePool objects represent the json object that is returned from *GET /1.0/storage-pools/<name>* and then the associated methods that are then available at the same endpoint.

There are also StorageResource and StorageVolume objects that represent the storage resources end-point for a pool at *GET /1.0/storage-pools/<pool>/resources* and a storage volume on a pool at *GET /1.0/storage-pools/<pool>/volumes/<type>/<name>. Note that these should be accessed from the storage pool object. For example:* 

```
client = pylxd.Client()
storage_pool = client.storage_pools.get('poolname')
storage_volume = storage_pool.volumes.get('custom', 'volumename')
```

**Note:** For more details of the LXD documentation concerning storage pools please see LXD Storage Pools REST API Documentation and LXD Storage Pools Documentation. This provides information on the parameters and attributes in the following methods.

**Note:** Please see the pylxd API documentation for more information on storage pool methods and parameters. The following is a summary.

#### 12.1.1 Storage Pool Manager methods

Storage-pools can be queried through the following client manager methods:

- *all()* Return a list of storage pools.
- get() Get a specific storage-pool, by its name.
- exists() Return a boolean for whether a storage-pool exists by name.
- create() Create a storage-pool. Note the config in the create class method is the WHOLE json object described as 'input' in the API docs. e.g. the 'config' key in the API docs would actually be config.config as passed to this method.

### 12.1.2 Storage-pool Object attributes

For more information about the specifics of these attributes, please see the LXD Storage Pools REST API documentation.

- name the name of the storage pool
- driver the driver (or type of storage pool). e.g. 'zfs' or 'btrfs', etc.
- used\_by which containers (by API endpoint /1.0/containers/<name>) are using this storage-pool.
- config a dictionary with some information about the storage-pool. e.g. size, source (path), volume.size, etc.
- managed Boolean that indicates whether LXD manages the pool or not.

### 12.1.3 Storage-pool Object methods

The following methods are available on a Storage Pool object:

- save save a modified storage pool. This saves the *config* attribute in it's entirety.
- *delete* delete the storage pool.
- put Change the LXD storage object with a passed parameter. The object is then synced back to the storage pool object.
- patch A more fine grained patch of the object. Note that the object is then synced back after a successful patch.

**Note:** raw\_put and raw\_patch are available (but not documented) to allow putting and patching without syncing the object back.

## 12.2 Storage Resources

Storage Resources are accessed from the storage pool object:

```
resources = storage_pool.resources.get()
```

Resources are read-only and there are no further methods available on them.

# 12.3 Storage Volumes

Storage Volumes are stored in storage pools. On the pylxd API they are accessed from a storage pool object:

```
storage_pool = client.storage_pools.get('pool1')
volumes = storage_pool.volumes.all()
named_volume = storage_pool.volumes.get('custom', 'vol1')
```

## 12.3.1 Methods available on <storage\_pool\_object>.volumes

The following methods are accessed from the *volumes* attribute on the storage pool object.

- all get all the volumes on the pool.
- get a get a single, type + name volume on the pool.
- create create a volume on the storage pool.

**Note:** Note that storage volumes have a tuple of *type* and *name* to uniquely identify them. At present LXD recognises three types (but this may change), and these are *container*, *image* and *custom*. LXD uses *container* and *image* for containers and images respectively. Thus, for user applications, *custom* seems like the type of choice. Please see the LXD Storage Pools documentation for further details.

## 12.3.2 Methods available on the storage volume object

Once in possession of a storage volume object from the *pylxd* API, the following methods are available:

- *rename* Rename a volume. This can also be used to migrate a volume from one pool to the other, as well as migrating to a different LXD instance.
- put Put an object to the LXD server using the storage volume details and then re-sync the object.
- patch Patch the object on the LXD server, and then re-sync the object back.
- save after modifying the object in place, use a PUT to push those changes to the LXD server.
- delete delete a storage volume object. Note that the object is, therefore, stale after this action.

**Note:** raw\_put and raw\_patch are available (but not documented) to allow putting and patching without syncing the object back.

# CHAPTER 13

Clustering

LXD supports clustering. There is only one cluster object.

# 13.1 Cluster object

The Cluster object represents the json object that is returned from *GET/1.0/cluster*.

There is also a ClusterMember and object that represents a cluster member at *GET /1.0/cluster/members*. Note that it should be accessed from the cluster object. For example:

```
client = pylxd.Client()
cluster = client.cluster.get()
member = cluster.members.get('node-5')
```

**Note:** Please see the pylxd API documentation for more information on storage pool methods and parameters. The following is a summary.

### 13.1.1 Cluster methods

A cluster can be queried through the following client manager methods:

• get() - Returns the cluster.

# 13.1.2 Cluster Object attributes

For more information about the specifics of these attributes, please see the LXD Cluster REST API documentation.

- server\_name the name of the server in the cluster
- enabled if the node is enabled

• member\_config - configuration information for new cluster members.

## 13.2 Cluster Members

Cluster Members are stored in a cluster. On the pylxd API they are accessed from a cluster object:

```
cluster = client.cluster.get()
members = cluster.members.all()
named_member = cluster.members.get('membername')
```

## 13.2.1 Methods available on <cluster\_object>.members

The following methods are accessed from the *members* attribute on the cluster object.

- all get all the members of the cluster.
- get a get a single named member of the cluster.

# 13.2.2 Cluster Member Object attributes

For more information about the specifics of these attributes, please see the LXD Cluster REST API documentation.

- server\_name the name of the server in the cluster
- url the url the lxd endpoint
- database if the distributed database is replicated on this node
- status if the member is off or online
- message a general message

# Contributing

pyLXD development is done on Github. Pull Requests and Issues should be filed there. We try and respond to PRs and Issues within a few days.

If you would like to contribute major features or have big ideas, it's best to post at the Linux Containers disucssion forum to discuss your ideas before submitting PRs. If you use [pylxd] in the title, it'll make it clearer.

# 14.1 Adding a Feature or Fixing a Bug

The main steps are:

- 1. There needs to be a bug filed on the Github repository. This is also for a feature, so it's clear what is being proposed prior to somebody starting work on it.
- 2. The pyLXD repository must be forked on Github to the developer's own account.
- 3. The developer should create a personal branch, with either:
  - feature/name-of-feature
  - bug/number/descriptive-name-of-bug

This can be done with git checkout -b feature/name-of-feature from the master branch.

- 4. Work on that branch, push to the personal GitHub repository and then create a Pull Request. It's a good idea to create the Pull Request early, particularly for features, so that it can be discussed and help sought (if needed).
- 5. When the Pull Request is ready it will then be merged.
- 6. At regular intervals the pyLXD module will be released to PyPi with the new features and bug fixes.

# 14.2 Requirements to merge a Pull Request (PR)

In order for a Pull Request to be merged the following criteria needs to be met:

- 1. All of the commits in the PR need to be signed off using the '-s' option with git commit. This is a requirement for all projects in the Github Linux Containers projects space.
- 2. Unit tests are required for the changes. These are in the pylxd/tests directory and follow the same directory structure as the module.
- 3. The unit test code coverage for the project shouldn't drop. This means that any lines that aren't testable (for good reasons) need to be explicitly excluded from the coverage using # NOQA comments.
- 4. If the feature/bug fix requires integration test changes, then they should be added to the integration directory.
- 5. If the feature/bug fix changes the API then the documentation in the doc/source directory should also be updated.
- 6. If the contributor is new to the project, then they should add their name/details to the CONTRIBUTORS.rst file in the root of the repository as part of the PR.

Once these requirements are met, the change will be merged to the repository. At this point, the contributor should then delete their private branch.

### 14.3 Code standards

pyLXD formats code with Black and isort. Verify the formatting with:

```
tox -e lint
```

If it fails, you can reformat the code with:

tox -e format

# 14.4 Testing

Testing pyLXD is in 3 parts:

- 1. Conformance with Black and isort, using the tox -e lint command.
- 2. Unit tests using tox -e py.
- 3. Integration tests using the tox -e integration-in-lxd.

**Note:** all of the tests can be run by just using the tox command on it's own, with the exception of the integration tests. These are not automatically run as they require a working LXD environment.

All of the commands use the Tox automation project to run tests in a sandboxed environment.

## 14.4.1 Unit Testing

pyLXD tries to follow best practices when it comes to testing. PRs are gated by GitHub Actions and CodeCov. It's best to submit tests with new changes, as your patch is unlikely to be accepted without them.

To run the tests, you should use Tox:

t ox

# 14.4.2 Integration Testing

Integration testing requires a running LXD system. They can be tested locally in LXD container with nesting support; tox -e integration-in-lxd.

14.4. Testing 39

# CHAPTER 15

# **API** documentation

### 15.1 Client

class pylxd.client.Client(endpoint=None, version='1.0', cert=None, verify=True, timeout=None, *project=None*)
Client class for LXD REST API.

This client wraps all the functionality required to interact with LXD, and is meant to be the sole entry point.

#### instances

A models. Instance.

#### containers

A models.Container.

#### virtual machines

A models. Virtual Machine.

### images

A models. Image.

### operations

A models. Operation.

#### profiles

A models.Profile.

### projects

A models. Project.

#### api

This attribute provides tree traversal syntax to LXD's REST API for lower-level interaction.

Use the name of the url part as attribute or item of an api object to create another api object appended with the new url part name, ie:

```
>>> api = Client().api
# /
>>> response = api.get()
# Check status code and response
>>> print response.status_code, response.json()
# /instances/test/
>>> print api.instances['test'].get().json()
```

#### assert\_has\_api\_extension(name)

Asserts that the *name* api\_extension exists. If not, then is raises the LXDAPIExtensionNotAvailable error.

**Parameters** name (str) – the api\_extension to test for

Returns None

Raises pylxd.exceptions.LXDAPIExtensionNotAvailable

events (websocket\_client=None, event\_types=None)

Get a websocket client for getting events.

/events is a websocket url, and so must be handled differently than most other LXD API endpoints. This method returns a client that can be interacted with like any regular python socket.

An optional websocket\_client parameter can be specified for implementation-specific handling of events as they occur.

#### **Parameters**

- websocket\_client (ws4py.client import WebSocketBaseClient) Optional websocket client can be specified for implementation-specific handling of events as they occur.
- **event\_types** (Set [EventType]) Optional set of event types to propagate. Omit this argument or specify {EventTypes.All} to receive all events.

**Returns** instance of the websocket client

Return type Option[\_WebsocketClient(), :param:'websocket\_client']

```
has_api_extension (name)
```

Return True if the *name* api extension exists.

**Parameters** name (str) – the api\_extension to look for.

**Returns** True if extension exists

Return type bool

# 15.2 Exceptions

```
class pylxd.exceptions.LXDAPIException(response)
```

A generic exception for representing unexpected LXD API responses.

LXD API responses are clearly documented, and are either a standard return value, and background operation, or an error. This exception is raised on an error case, or when the response status code is not expected for the response.

This exception should *only* be raised in cases where the LXD REST API has returned something unexpected.

```
class pylxd.exceptions.NotFound(response)
```

An exception raised when an object is not found.

#### class pylxd.exceptions.ClientConnectionFailed

An exception raised when the Client connection fails.

### 15.3 Certificate

#### classmethod all(client)

Get all certificates.

classmethod create (client, password, cert\_data)

Create a new certificate.

classmethod get (client, fingerprint)

Get a certificate by fingerprint.

### 15.4 Container

```
class pylxd.models.Instance(*args, **kwargs)
```

An LXD Instance.

This class is not intended to be used directly, but rather to be used via Client.instance.create.

#### class FilesManager (instance)

A pseudo-manager for namespacing file operations.

```
delete_available()
```

File deletion is an extension API and may not be available. https://github.com/lxc/lxd/blob/master/doc/api-extensions.md#file\_delete

```
mk_dir (path, mode=None, uid=None, gid=None)
```

Creates an empty directory on the container. This pushes an empty directory to the containers file system named by the *filepath*. :param path: The path in the container to to store the data in. :type path: str :param mode: The unit mode to store the file with. The default of

None stores the file with the current mask of 0700, which is the lxd default.

#### **Parameters**

- **uid** (*int*) The uid to use inside the container. Default of None results in 0 (root).
- gid (int) The gid to use inside the container. Default of None results in 0 (root).

Raises LXDAPIException if something goes wrong

put (filepath, data, mode=None, uid=None, gid=None)

Push a file to the instance.

This pushes a single file to the instances file system named by the *filepath*.

#### **Parameters**

- **filepath** (str) The path in the instance to to store the data in.
- data (bytes or str) The data to store in the file.
- mode (Union[oct, int, str]) The unit mode to store the file with. The default of None stores the file with the current mask of 0700, which is the lxd default.
- **uid** (*int*) The uid to use inside the instance. Default of None results in 0 (root).
- gid (int) The gid to use inside the instance. Default of None results in 0 (root).

Raises LXDAPIException if something goes wrong

15.3. Certificate 43

#### recursive\_get (remote\_path, local\_path)

Recursively pulls a directory from the container. Pulls the directory named *remote\_path* from the container and creates a local folder named *local\_path* with the content of *remote\_path*. If *remote\_path* is a file, it will be copied to *local\_path*. :param remote\_path: The directory path on the container. :type remote\_path: str :param local\_path: The path at which the directory will be stored. :type local\_path: str :return: :raises: LXDAPIException if an error occurs

recursive\_put (src, dst, mode=None, uid=None, gid=None)

Recursively push directory to the instance.

Recursively pushes directory to the instances named by the dst

#### **Parameters**

- **src** (*str*) The source path of directory to copy.
- **dst** (str) The destination path in the instance of directory to copy
- mode (Union[oct, int, str]) The unit mode to store the file with. The default of None stores the file with the current mask of 0700, which is the lxd default.
- **uid** (int) The uid to use inside the instance. Default of None results in 0 (root).
- gid(int) The gid to use inside the instance. Default of None results in 0 (root).

Raises NotADirectoryError if src is not a directory

Raises LXDAPIException if an error occurs

#### classmethod all(client)

Get all instances.

Instances returned from this method will only have the name set, as that is the only property returned from LXD. If more information is needed, *Instance.sync* is the method call that should be used.

classmethod create (client, config, wait=False, target=None)

Create a new instance config.

#### **Parameters**

- client (Client) client instance
- **config** (*dict*) The configuration for the new instance.
- wait (bool) Whether to wait for async operations to complete.
- **target** (*str*) If in cluster mode, the target member.

Raises LXDAPIException – if something goes wrong.

**Returns** an instance if successful

Return type Instance

**execute** (commands, environment=None, encoding=None, decode=True, stdin\_payload=None, stdin\_encoding='utf-8', stdout\_handler=None, stderr\_handler=None)

Execute a command on the instance. stdout and stderr are buffered if no handler is given.

#### **Parameters**

- **commands** ([str]) The command and arguments as a list of strings
- **environment** ({str: str}) The environment variables to pass with the command
- **encoding** (str) The encoding to use for stdout/stderr if the param decode is True. If encoding is None, then no override is performed and whatever the existing encoding from LXD is used.
- **decode** (bool) Whether to decode the stdout/stderr or just return the raw buffers.

- stdin\_payload (Can be a file, string, bytearray, generator or ws4py Message object) Payload to pass via stdin
- **stdin\_encoding** Encoding to pass text to stdin (default utf-8)
- **stdout\_handler** (Callable[[str], None]) Callable than receive as first parameter each message received via stdout
- **stderr\_handler** (Callable[[str], None]) Callable than receive as first parameter each message received via stderr

**Raises** ValueError – if the ws4py library is not installed.

**Returns** A tuple of (exit\_code, stdout, stderr)

**Return type** \_InstanceExecuteResult() namedtuple

```
classmethod exists(client, name)
```

Determine whether a instance exists.

freeze (timeout=30, force=True, wait=False)

Freeze the instance.

#### generate\_migration\_data(live=False)

Generate the migration data.

This method can be used to handle migrations where the client connection uses the local unix socket. For more information on migration, see *Instance.migrate*.

**Parameters** live (bool) – Whether to include "live": "true" in the migration

Raises LXDAPIException if the request to migrate fails

**Returns** dictionary of migration data suitable to send to an new client to complete a migration.

**Return type** Dict[str, ANY]

```
classmethod get (client, name)
```

Get a instance by name.

```
migrate (new_client, live=False, wait=False)
```

Migrate a instance.

Destination host information is contained in the client connection passed in.

If the *live* param is True, then a live migration is attempted, otherwise a non live one is running.

If the instance is running for live migration, it either must be shut down first or criu must be installed on the source and destination machines and the *live* param should be True.

#### **Parameters**

- new\_client (pylxd.client.Client) the pylxd client connection to migrate the instance to.
- **live** (bool) whether to perform a live migration
- wait (bool) if True, wait for the migration to complete

**Raises** LXDAPIException if any of the API calls fail.

Raises ValueError if source of target are local connections

**Returns** the response from LXD of the new instance (the target of the migration and not the operation if waited on.)

Return type requests. Response

15.4. Container 45

```
publish (public=False, wait=False)
```

Publish a instance as an image.

The instance must be stopped in order publish it as an image. This method does not enforce that constraint, so a LXDAPIException may be raised if this method is called on a running instance.

If wait=True, an Image is returned.

```
raw_interactive_execute (commands, environment=None)
```

Execute a command on the instance interactively and returns urls to websockets. The urls contain a secret uuid, and can be accesses without further authentication. The caller has to open and manage the websockets themselves.

#### **Parameters**

- commands ([str]) The command and arguments as a list of strings (most likely a shell)
- **environment** ({str: str}) The environment variables to pass with the command

**Returns** Two urls to an interactive websocket and a control socket

```
Return type {'ws':str,'control':str}
```

```
rename (name, wait=False)
```

Rename an instance.

```
restart (timeout=30, force=True, wait=False)
```

Restart the instance.

```
restore_snapshot (snapshot_name, wait=False)
```

Restore a snapshot using its name.

Attempts to restore a instance using a snapshot previously made. The instance should be stopped, but the method does not enforce this constraint, so an LXDAPIException may be raised if this method fails.

#### **Parameters**

- **snapshot\_name** (*str*) the name of the snapshot to restore from
- wait (boolean) wait until the operation is completed.

**Raises** LXDAPIException if the operation fails.

**Returns** the original response from the restore operation (not the operation result)

```
Return type requests. Response
```

```
start (timeout=30, force=True, wait=False)
```

Start the instance.

```
stop (timeout=30, force=True, wait=False)
```

Stop the instance.

```
unfreeze(timeout=30, force=True, wait=False)
```

Unfreeze the instance.

```
class pylxd.models.Container(*args, **kwargs)
```

Flavour of models. Instance for containers.

```
class pylxd.models.Snapshot(client, **kwargs)
```

A instance snapshot.

```
publish (public=False, wait=False)
```

Publish a snapshot as an image.

If wait=True, an Image is returned.

This functionality is currently broken in LXD. Please see https://github.com/lxc/lxd/issues/2201 - The implementation here is mostly a guess. Once that bug is fixed, we can verify that this works, or file a bug to fix it appropriately.

```
rename (new name, wait=False)
```

Rename a snapshot.

```
restore(wait=False)
```

Restore this snapshot.

Attempts to restore a instance using this snapshot. The instance should be stopped, but the method does not enforce this constraint, so an LXDAPIException may be raised if this method fails.

**Parameters wait** (boolean) – wait until the operation is completed.

Raises LXDAPIException if the the operation fails.

**Returns** the original response from the restore operation (not the operation result)

Return type requests. Response

## 15.5 Virtual Machine

```
class pylxd.models.VirtualMachine(*args, **kwargs)
Flavour of models.Instance for VMs.
```

# **15.6 Image**

```
class pylxd.models.Image (client, **kwargs)
    A LXD Image.

add_alias (name, description)
    Add an alias to the image.

classmethod all (client)
    Get all images.

copy (new_client, public=None, auto_update=None, wait=False)
    Copy an image to a another LXD.
```

Destination host information is contained in the client connection passed in.

```
classmethod create (client, image_data, metadata=None, public=False, wait=True)

Create an image.
```

If metadata is provided, a multipart form data request is formed to push metadata and image together in a single request. The metadata must be a tar achive.

wait parameter is now ignored, as the image fingerprint cannot be reliably determined consistently until after the image is indexed.

```
 \begin{array}{c} \textbf{classmethod create\_from\_simplestreams} \ (client, & server, & alias, & public=False, \\ & auto\_update=False) \\ \\ \textbf{Copy an image from simplestreams}. \end{array}
```

15.5. Virtual Machine 47

```
classmethod create_from_url (client, url, public=False, auto_update=False)
```

Copy an image from an url.

#### delete\_alias (name)

Delete an alias from the image.

#### classmethod exists (client, fingerprint, alias=False)

Determine whether an image exists.

If alias is True, look up the image by its alias, rather than its fingerprint.

#### export()

Export the image.

Because the image itself may be quite large, we stream the download in 1kb chunks, and write it to a temporary file on disk. Once that file is closed, it is deleted from the disk.

### classmethod get(client, fingerprint)

Get an image.

#### classmethod get\_by\_alias(client, alias)

Get an image by its alias.

## 15.7 Network

```
class pylxd.models.Network(client, **kwargs)
```

Model representing a LXD network.

#### classmethod all(client)

Get all networks.

Parameters client (Client) - client instance

Return type list[Network]

classmethod create (client, name, description=None, type=None, config=None)

Create a network.

#### **Parameters**

- client (Client) client instance
- name (str) name of the network
- **description** (str) description of the network
- **type** (str) type of the network
- config (dict) additional configuration

### ${\tt classmethod\ exists}\ ({\it client}, {\it name})$

Determine whether network with provided name exists.

#### **Parameters**

- client (Client) client instance
- name (str) name of the network

**Returns** *True* if network exists, *False* otherwise

Return type bool

```
classmethod get (client, name)
     Get a network by name.
         Parameters
             • client (Client) - client instance
             • name (str) - name of the network
         Returns network instance (if exists)
         Return type Network
         Raises NotFound if network does not exist
rename (new name)
     Rename a network.
         Parameters new_name (str) – new name of the network
         Returns Renamed network instance
         Return type Network
save (*args, **kwargs)
     Save data to the server.
     This method should write the new data to the server via marshalling. It should be a no-op when the object
     is not dirty, to prevent needless I/O.
state()
     Get network state.
```

# 15.8 Operation

```
class pylxd.models.Operation(**kwargs)
    An LXD operation.
```

If the LXD server sends attributes that this version of pylxd is unaware of then a warning is printed. By default the warning is issued ONCE and then supressed for every subsequent attempted setting. The warnings can be completely suppressed by setting the environment variable PYLXD\_WARNINGS to 'none', or always displayed by setting the PYLXD\_WARNINGS variable to 'always'.

```
classmethod get (client, operation_id)
    Get an operation.

wait ()
    Wait for the operation to complete and return.

classmethod wait_for_operation (client, operation_id)
    Get an operation and wait for it to complete.
```

# 15.9 Profile

```
class pylxd.models.Profile(client, **kwargs)
    A LXD profile.
    classmethod all(client)
        Get all profiles.
```

15.8. Operation 49

```
classmethod create (client, name, config=None, devices=None)
     Create a profile.
classmethod exists(client, name)
     Determine whether a profile exists.
classmethod get (client, name)
     Get a profile.
rename (new name)
    Rename the profile.
```

# 15.10 Project

```
class pylxd.models.Project(client, **kwargs)
     A LXD project.
     This corresponds to the LXD endpoint at /1.0/projects.
     api_extension: 'projects'
     classmethod all(client)
          Get all projects.
     classmethod create(client, name, description=None, config=None)
          Create a project.
     classmethod exists(client, name)
          Determine whether a project exists.
     classmethod get (client, name)
          Get a project.
     rename (new_name)
          Rename the project.
```

# 15.11 Storage Pool

```
class pylxd.models.StoragePool(*args, **kwargs)
     An LXD storage_pool.
     This corresponds to the LXD endpoint at /1.0/storage-pools
     api_extension: 'storage'
     classmethod all(client)
           Get all storage_pools.
           Implements GET /1.0/storage-pools
           Note that the returned list is 'sparse' in that only the name of the pool is populated. If any of the attributes
           are used, then the sync function is called to populate the object fully.
               Parameters client (pylxd.client.Client) - The pylxd client object
               Returns a storage pool if successful, raises NotFound if not found
```

**Return type** [pylxd.models.storage\_pool.StoragePool]

Raises pylxd.exceptions.LXDAPIExtensionNotAvailable if the 'storage' api extension is missing.

#### api

Provides an object with the endpoint:

/1.0/storage-pools/<self.name>

Used internally to construct endpoints.

Returns an API node with the named endpoint

```
Return type pylxd.client._APINode
```

#### classmethod create (client, definition)

Create a storage\_pool from config.

Implements POST /1.0/storage-pools

The definition parameter defines what the storage pool will be. An example config for the zfs driver is:

```
{
    "config": { "size": "10GB"
    }, "driver": "zfs", "name": "pool1"
```

Note that **all** fields in the *definition* parameter are strings.

For further details on the storage pool types see: https://lxd.readthedocs.io/en/latest/storage/

The function returns the a *StoragePool* instance, if it is successfully created, otherwise an Exception is raised.

#### **Parameters**

- client (pylxd.client.Client) The pylxd client object
- **definition** (dict) the fields to pass to the LXD API endpoint

Returns a storage pool if successful, raises NotFound if not found

```
Return type pylxd.models.storage_pool.StoragePool
```

**Raises** pylxd.exceptions.LXDAPIExtensionNotAvailable if the 'storage' api extension is missing.

Raises pylxd.exceptions.LXDAPIException if the storage pool couldn't be created.

#### delete()

Delete the storage pool.

Implements DELETE /1.0/storage-pools/<self.name>

Deleting a storage pool may fail if it is being used. See the LXD documentation for further details.

Raises pylxd.exceptions.LXDAPIException if the storage pool can't be deleted.

#### classmethod exists(client, name)

Determine whether a storage pool exists.

A convenience method to determine a pool exists. However, it is better to try to fetch it and catch the <code>pylxd.exceptions.NotFound</code> exception, as otherwise the calling code is like to fetch the pool twice. Only use this if the calling code doesn't *need* the actual storage pool information.

#### **Parameters**

- client (pylxd.client.Client) The pylxd client object
- name (str) the name of the storage pool to get

Returns True if the storage pool exists, False if it doesn't.

Return type bool

Raises pylxd.exceptions.LXDAPIExtensionNotAvailable if the 'storage' api extension is missing.

#### classmethod get (client, name)

Get a storage\_pool by name.

Implements GET /1.0/storage-pools/<name>

#### **Parameters**

- client (pylxd.client.Client) The pylxd client object
- name (str) the name of the storage pool to get

Returns a storage pool if successful, raises NotFound if not found

Return type pylxd.models.storage\_pool.StoragePool

Raises pylxd.exceptions.NotFound

**Raises** pylxd.exceptions.LXDAPIExtensionNotAvailable if the 'storage' api extension is missing.

patch (patch\_object, wait=False)

Patch the storage pool.

Implements PATCH /1.0/storage-pools/<self.name>

Patching the object allows for more fine grained changes to the config. The object is refreshed if the PATCH is successful. If this is *not* required, then use the client api directly.

#### **Parameters**

- patch\_object (dict) A dictionary. The most useful key will be the *config* key.
- wait (bool) Whether to wait for async operations to complete.

Raises pylxd.exceptions.LXDAPIException if the storage pool can't be modified.

put (put\_object, wait=False)

Put the storage pool.

Implements PUT /1.0/storage-pools/<self.name>

Putting to a storage pool may fail if the new configuration is incompatible with the pool. See the LXD documentation for further details.

Note that the object is refreshed with a *sync* if the PUT is successful. If this is *not* desired, then the raw API on the client should be used.

#### **Parameters**

- put\_object (dict) A dictionary. The most useful key will be the config key.
- wait (bool) Whether to wait for async operations to complete.

Raises pylxd.exceptions.LXDAPIException if the storage pool can't be modified.

```
save (wait=False)
```

Save the model using PUT back to the LXD server.

Implements PUT /1.0/storage-pools/<self.name> automagically

The fields affected are: *description* and *config*. Note that they are replaced in their *entirety*. If finer grained control is required, please use the patch () method directly.

Updating a storage pool may fail if the config is not acceptable to LXD. An LXDAPIException will be generated in that case.

Raises pylxd.exceptions.LXDAPIException if the storage pool can't be deleted.

### 15.12 Cluster

```
class pylxd.models.Cluster(*args, **kwargs)
    An LXD Cluster.

classmethod get(client, *args)
    Get cluster details

class pylxd.models.ClusterMember(client, **kwargs)
    A LXD cluster member.

classmethod all(client, *args)
    Get all cluster members.

classmethod get(client, server_name)
    Get a cluster member by name.
```

15.12. Cluster 53

# CHAPTER 16

# Indices and tables

- genindex
- modindex
- search

# Index

A add_alias() (pylxd.models.Image method), 47 all() (pylxd.models.Certificate class method), 43 all() (pylxd.models.ClusterMember class method), 53 all() (pylxd.models.Image class method), 47 all() (pylxd.models.Instance class method), 44 all() (pylxd.models.Network class method), 48 all() (pylxd.models.Profile class method), 49 all() (pylxd.models.Project class method), 50 all() (pylxd.models.StoragePool class method), 50 api (pylxd.client.Client attribute), 41 api (pylxd.models.StoragePool attribute), 51 assert_has_api_extension()	delete_alias() (pylxd.models.Image method), 48 delete_available()
Certificate (class in pylxd.models), 43 Client (class in pylxd.client), 41 ClientConnectionFailed (class in pylxd.exceptions), 42 Cluster (class in pylxd.models), 53 ClusterMember (class in pylxd.models), 53 Container (class in pylxd.models), 46	F freeze() (pylxd.models.Instance method), 45  G generate_migration_data()
containers (pylxd.client.Client attribute), 41 copy () (pylxd.models.Image method), 47 create() (pylxd.models.Certificate class method), 43 create() (pylxd.models.Image class method), 47 create() (pylxd.models.Instance class method), 44 create() (pylxd.models.Network class method), 48 create() (pylxd.models.Profile class method), 49 create() (pylxd.models.Project class method), 50 create() (pylxd.models.StoragePool class method), 51 create_from_simplestreams()	get () (pylxd.models.Cluster class method), 53 get () (pylxd.models.ClusterMember class method), 53 get () (pylxd.models.Image class method), 48 get () (pylxd.models.Instance class method), 45 get () (pylxd.models.Network class method), 48 get () (pylxd.models.Operation class method), 49 get () (pylxd.models.Profile class method), 50 get () (pylxd.models.Project class method), 50 get () (pylxd.models.StoragePool class method), 52 get_by_alias() (pylxd.models.Image class method),
<pre>(pylxd.models.Image class method), 47 create_from_url() (pylxd.models.Image class method), 47  D delete() (pylxd.models.StoragePool method), 51</pre>	H has_api_extension() (pylxd.client.Client method), 42

method), 46

```
S
Image (class in pylxd.models), 47
                                                      save() (pylxd.models.Network method), 49
images (pylxd.client.Client attribute), 41
                                                      save() (pylxd.models.StoragePool method), 52
Instance (class in pylxd.models), 43
                                                      Snapshot (class in pylxd.models), 46
Instance.FilesManager (class in pylxd.models),
                                                     start() (pylxd.models.Instance method), 46
                                                      state() (pylxd.models.Network method), 49
instances (pylxd.client.Client attribute), 41
                                                      stop () (pylxd.models.Instance method), 46
                                                      StoragePool (class in pylxd.models), 50
L
LXDAPIException (class in pylxd.exceptions), 42
                                                     unfreeze () (pylxd.models.Instance method), 46
M
                                                      V
migrate() (pylxd.models.Instance method), 45
                 (pylxd.models.Instance.FilesManager
                                                     virtual_machines (pylxd.client.Client attribute), 41
mk_dir()
        method), 43
                                                     VirtualMachine (class in pylxd.models), 47
Ν
                                                     W
Network (class in pylxd.models), 48
                                                     wait () (pylxd.models.Operation method), 49
NotFound (class in pylxd.exceptions), 42
                                                     wait_for_operation()
                                                                                  (pylxd.models.Operation
                                                               class method), 49
0
Operation (class in pylxd.models), 49
operations (pylxd.client.Client attribute), 41
patch() (pylxd.models.StoragePool method), 52
Profile (class in pylxd.models), 49
profiles (pylxd.client.Client attribute), 41
Project (class in pylxd.models), 50
projects (pylxd.client.Client attribute), 41
publish () (pylxd.models.Instance method), 45
publish() (pylxd.models.Snapshot method), 46
put () (pylxd.models.Instance.FilesManager method),
        43
put () (pylxd.models.StoragePool method), 52
R
raw_interactive_execute()
         (pylxd.models.Instance method), 46
recursive_get()(pylxd.models.Instance.FilesManager
        method), 43
recursive_put() (pylxd.models.Instance.FilesManager
        method), 44
rename () (pylxd.models.Instance method), 46
rename () (pylxd.models.Network method), 49
rename () (pylxd.models.Profile method), 50
rename() (pylxd.models.Project method), 50
rename () (pylxd.models.Snapshot method), 47
restart () (pylxd.models.Instance method), 46
restore() (pylxd.models.Snapshot method), 47
                              (pylxd.models.Instance
restore_snapshot()
```

58 Index